

> **Email** > **Email Clients**

# Setting Up Your Email in Windows (Vista) Mail

Print this Article


Comment on this Article

Last Updated: September 14, 2007 4:33 PM


You can set up Windows (Vista) Mail to work with your email account.

## To Set Up Your Email Account in Windows (Vista) Mail


1. In Microsoft Mail, from the **Tools** menu, select **Accounts**.




2. In the **Internet Accounts** window, click **Add** to add a new mail account.



3. On the **Your Name** page, in the **Display Name** field, enter your full name and then click **Next**.




4. On the **Internet Email Address** page, in the **Email address** field, enter your email address and then click **Next**.



5. On the **Set up Email Servers** page, enter your information as follows and then click **Next**.  
**Incoming email server type**  
Select **POP3** from the drop down list.

**Incoming mail (POP3 or IMAP) server**  
Type **pop.secureserver.net**.

**Outgoing email server (SMTP) name**  
Type **smtpout.secureserver.net** and select **Outgoing server requires authentication**.



**Set up e-mail servers**

Incoming e-mail server type:  
POP3

Incoming mail (POP3 or IMAP) server:  
pop.secureserver.net


Outgoing e-mail server (SMTP) name:  
smtpout.secureserver.net

Outgoing server requires authentication

[Where can I find my e-mail server information?](#)

Next Cancel

6. On the **Internet Mail Logon** page, in the **Email Username** and **Password** fields, enter your email address and password for your email account, and then click **Next**.



**Internet Mail Logon**

Type the account name and password your Internet service provider has given you.


E-mail username: janesmith@coolexample.com

Password: ●●●●●●


Remember password

Next Cancel


7. Click **Finish**.




8. Return to Microsoft Mail, and from the **Tools** menu, select **Accounts**.



9. In the **Internet Accounts** window, under your list of Mail accounts, select the account you just set up and then click **Properties**.



10. In the **Properties** window, go to the **Advanced** tab.
11. Under **Server Port Numbers**, in the **Outgoing mail (SMTP)** field, type **80** and then click **OK**.



If you have trouble sending mail, try setting your Outgoing mail (SMTP) server port to 25 or 3535.

Copyright © 2005 - 2008. All rights reserved.